

NAME

dvilj4, **dvilj4l**, **dvilj2p**, **dvilj** – convert a TeX DVI file to PCL, for HP LaserJet printers

SYNOPSIS

```
dvilj [--Dnumber] [-ccopies] [-dmode] [-D] [-E] [-eoutputfile]
      [-ffrompage] [-g] [-hheaderfile] [-l] [-Mflag] [-mmag] [-ppages]
      [-q] [-r] [-ttopage] [-spagesize] [-v] [-Vmode] [-w] [-xxoff(mm)]
      [-yyoff(mm)] [-Xxoff(dots)] [-Yyoff(dots)] [-z] [filename]
```

DESCRIPTION

dvilj and siblings convert TeX-output .dvi files into PCL (the Hewlett-Packard Printer Control Language) commands suitable for printing on a HP LaserJet+, HP LaserJet IIP (using **dvilj2p**), HP LaserJet 4 (using **dvilj4**), and fully compatible printers.

dvilj4 also provides support for the builtin Intellifont and TrueType fonts; TFM and VF files are provided in the distribution. Virtual fonts are not supported directly by **dvilj**, so you must run *dvicopy* (1) first, or otherwise expand the virtual fonts

All programs are generated from one source file *dvi2xx.c*. They are usually called via a shell script or as a line printer filter. One such script, *dvihp* (1), is included in the distribution. It provides command-line options similar to those of *dvips* (1).

OPTIONS

--Dnumber

Debug according to the bits of *number*; see the *kpathsea* (3) manual for values. Also turns on general verbosity.

-cnumber

Print each page *number* times (including original)

-dnumber

print in duplex mode. The option **-d1** means long edge binding, **-d2** stands for short edge binding. This option is only selectable in **dvilj4** and **dvilj2p**.

-D[–12]

Double-sided printing – see below; **-D1** prints odd sides only, **-D2** is for even pages, a trailing – suppresses printing of empty padding pages.

-E Switch printer into econo mode (**dvilj4** only).

-eoutfile

Send output to *outfile* instead of the basename of dvi file extended with .lj. If outfile is – (as in **-e–**) the output is directed to standard output and can be directly piped into a spooler.

-fpagenum

Print pages with TeX page numbers greater than or equal to *pagenum*.

-g Go mode: do not reset printer at start of job.

-hheaderfile

Copy *headerfile* to output before translation of the DVI file. Used to send arbitrary commands to the laserprinter.

-l Print output in landscape mode; supported only by **dvilj2p** and **dvilj4**.

-Mflag

Do (not) call *mktexpk*(1) to generate fonts on demand. **-M1** and **-M** are equivalent. **-M0** enables invoking *mktexpk*(1). (This is the same as in *dvips*(1).) The default behavior (i.e., if no **-M** option is given) is chosen at compile-time; as distributed, mktexpk is enabled.

-mmagnification

Specify the magnification to use. The following are available:

```
-m#usermag e.g., #900
-m0 equivalent to -m#1000
-mh equivalent to -m#1095
-m1 equivalent to -m#1200
-mq equivalent to -m#1250
-m2 equivalent to -m#1440
-m3 equivalent to -m#1728
-m4 equivalent to -m#2074
-m5 equivalent to -m#2488
```

-ppagecount

Print *pagecount* pages after the starting page.

-q Quiet operation: omit final statistics, etc.**-r** Toggle page reversal.**-spagesize**

Specify the page size:

```
-s1: Executive (7.25" x 10.5")
-s2: Letter (8.5" x 11")
-s3: Legal (8.5" x 14")
-s6: Ledger (11" x 17")
-s25: A5 paper (148mm x 210mm)
-s26: A4 paper (210mm x 297mm)
-s27: A3 (297mm x 420mm)
-s45: JIS B5 paper (182mm x 257mm)
-s46: JIS B4 paper (250mm x 354mm)
-s71: Hagaki postcard (100mm x 148mm)
-s72: Oufuku-Hagaki postcard (200mm x 148mm)
-s80: Monarch Envelope (3 7/8" x 7 1/2")
-s81: Commercial Envelope 10 (4 1/8" x 9 1/2")
-s90: International DL (110mm x 220mm)
-s91: International C5 (162mm x 229mm)
-s100: International B5 (176mm x 250mm)
```

These values are from the PCL 5 technical reference manual. If the **-s** commandline option is omitted, no clipping is performed at the bottom of the page. (But printing below the paper bottom should not disturb any correctly behaving PCL printer.) Please remember that the correct paper tray must be installed for selected paper size, so use this option only if you have full control over your print destination.

- tpagenum**
Print pages with TeX page numbers less than or equal to *pagenum*.
- v** Verbose mode: list fonts used, etc.
- Vmode**
Compatibility mode. As *mode*, use K for Kyocera, B for Brother, 6 for LJ6 printers.
- w** Omit warnings.
- xoffset**
Global x–offset in mm on output page relative to 1 inch/1 inch origin.
- yoffset**
Global y–offset in mm on output page relative to 1 inch/1 inch origin.
- Xoffset**
Global x–offset in dots on output page (overrides 1 inch/1 inch origin).
- Yoffset**
Global y–offset in dots on output page (overrides 1 inch/1 inch origin).
- z** Print a test page with the page counter at end of job.

OPERANDS

If no operands are specified a brief usage message is displayed.

filename

The DVI file name that shall be converted by **dvilj**. It must always be seekable.

The output file name is constructed from *filename*. Either an extension `.dvi` is replaced by `.lj`, or the extension `.lj` is appended.

If *filename* is `–`, the DVI file is read from standard input and the resulting PCL document is written to standard output. (Please remember that the DVI file must be seekable, even if it's stdin.)

SUPPORTED TeX \special COMMANDS

\special commands supported by **dvilj** have the generic syntax

```
\special{key1=value key1="value with space"}
\special{key3 = value key4 = 'note optional spaces around equal sign'}
```

I.e., specials are a sequence of key/value pairs, separated by an equal sign. Spaces around the equal sign are ignored. The value is either a space separated word, or a quoted string. Both double and single quotes can be used, alternatively. There is no support for quoting quote characters in values; if you want both double and single quotes in one value, you're out of luck.

The following key/value combinations are valid:

hpfile=*file*

Insert *file* at the current position. *file* is searched with *kpathsea* (3), see below.

The file content must be valid for this printer, i.e., it should contain PCL escape sequences or HP–GL/2 commands. If the file is a graphics file, this typically means that the upper left corner of the graphics is placed at the current position.

PCL absolute positioning escape sequences in *file* are rewritten to be relative positioning commands; the lowest appearing coordinate is used as reference.

hfile_verbatim=file

Insert *file* verbatim at the current position, without any changes of the file content. *file* is searched with *kpathsea* (3), see below.

This is mostly used to keep absolute positions in PCL files.

psfile=file llx=x0 lly=y0 urx=x1 ury=y1 rwi=s

Convert Postscript file *file* to HP PCL, by Ghostscript with device `ljetplus`, and insert the resulting graphics file at the current position, rewriting absolute position escape sequences. *file* is searched with *kpathsea* (3), see below.

The accompanying key/value pairs are mandatory, they can be specified in an arbitrary order. Values *x0*, *x1*, *y0*, *y1*, and *s* are integers. (*x0*,*y0*) is the lower left corner, (*x1*,*y1*) the upper right corner of the image.

Please note: The specific semantics of this special is not known. In particular, the **rwi** parameter is some scale factor; but even looking at the source code it is not quite clear what the special's author intended to implement here. In addition, it is unclear what dimensions are used to specify the corners, Postscript points or PCL dots.

If you happen to know the psfile semantics, or if you spent the work analyzing them, please inform us at tex-k@tug.org, so that we can update this man page with the relevant information.

dvilj-psfile-syntax=syntax

where *syntax* is either `dvilj` or `ignore`. This is a very crude way to tell the driver what to do with **psfile** specials.

If the value is `ignore`, all **psfile** specials that are processed afterwards are ignored, until the next **dvilj-psfile-syntax** special is processed.

If the value is `dvilj`, **psfiles** specials are processed as explained above, until the next **dvilj-psfile-syntax** special is processed.

An obvious, planned, extension is the value `dvips`, but this has not been implemented yet.

That special is not as simple as it sounds at first. Since its semantics is defined by processing order, it is only of use if it is placed on the same page as the **psfile** special. Having it once in a file (e.g., on the first page) does not help if you print just one page of the document — **dvilj** does not do prescanning of first-page specials like some other drivers do. (Patches would be welcome, of course.)

comment=arbitrary text**comment** *arbitrary text*

This causes the rest of the special to be ignored; it may be used to add meta-information to a DVI file.

With the first form, the comment may appear anywhere in the special. When it appears first, the processing of this special is terminated and all other text behind is ignored.

The second form is a speciality that has been introduced for compatibility with other drivers. If the first keyword of the special is **comment** and has no value, it is taken as a valid comment syntax, too; the rest of the special is ignored.

orientation=*po*

Position the page on the physical paper. The value *po* may be one of the following values:

- 0 for portrait
- 1 for landscape
- 2 for reverse portrait
- 3 for reverse landscape

defpoint=*n(x,y)*

Define the point number *n*. This point can be referred to later in other special commands to specify areas that shall be filled with some pattern. *n* must be between 0 and 79.

x and *y* are the position of that point and have the form ?pt where ? is a floating point number. The positions are relative to the DVI page origin; i.e., coordinates increase moving right and down, the point of origin is (1in,1in) in the upper left corner, altered by options **-x**, **-y**, **-X**, and **-Y**, but not by \offset and \voffset.

x and *y* can be omitted, i.e., the values 3 or 4 (,) are valid. Then the current page position is used as position for point *n*.

resetpoints=all

This undefines all points again.

gray=gray_scale**grey=gray_scale**

This sets the fill mode for the next **fill** special, the area will be filled with gray color. (**grey** is an alias for **gray**.) Any pattern specification is reset.

gray_scale is the percentage of gray that shall be used here; with 0 meaning white and 100 meaning black.

Caveat: That special is actually a misnomer. PCL names these gray scales *shading patterns* and they are created by placing dots in the area. The gray scale selects how far spread the dots are. In the lower ranges, this doesn't look very gray on close sight, but more like a dotted background. Furthermore, the gray scales are not as fine-grained as the value range 0..100 might make you believe. In reality, there are only 8 different gray patterns available:

- 1 - 2%
- 3 - 10%
- 11 - 20%
- 21 - 35%
- 36 - 55%
- 56 - 80%
- 81 - 99%
- 100%

One of these patterns is selected according to the *gray_scale* value.

pattern=pat

This sets the fill mode for the next **fill** special, the area will be filled with a pattern. Any gray color specification is reset.

pat is one of the following values:

- 1 horizontal lines
- 2 vertical lines
- 3 diagonal lines, from lower left corner to upper right corner
- 4 diagonal lines, from upper right corner to lower left corner
- 5 crossed lines, vertically
- 6 crossed lines, diagonally

fill=*a/b*

Fill the area between the points *a* and *b*, according to the current fill mode.

Point *a* **must** be the upper left corner and point *b* **must** be the lower left corner of the rectangle. Otherwise the result is garbage.

The default fill mode is 10% gray color filling.

filename

This is a legacy special, its use is depreciated. If the special is just one word that names an existing file, that file is verbatim included. Contrary to other file inclusion means, the file is not searched with *kpathsea* (3). *You are not supposed to use this special and we won't fix any problems with it.*

It should be noted that the special parser does sometimes accept constructs that are not valid as in the documentation above. Then, the output is most often damaged in some way.

Searching for Included Files

Proper file include specials search the file with *kpathsea* (3). The search path is configured by variable `DVILJINPUTS` and, if the file is not found in that search path, by variable `TEXINPUTS`.

Search via `DVILJINPUTS` covers the use case that one has common site-wide graphics that shall be included in documents, e.g., scanned signatures. Search via `TEXINPUTS` covers the use case that one has graphics as part of ones current document.

`dvilj` is used as the `.PROGRAM` name in *texmf.cnf*, for all driver variants, independent of the actual program name.

Unknown Specials and `TEX_HUSH` configuration

Kpathsea (3) has the concept of warning suppression with the configuration variable `TEX_HUSH`, please refer to its Info node *TeX support / Suppressing warnings*. That variable holds a colon-separated identifiers that specifies the to-be-suppressed warnings.

If `special` is among the listed values, **dvilj** does not output warnings any more about specials that it doesn't know about. But if there is a recognized special and if that special has an invalid parameter, then a warning is output nevertheless, independent of the content of `TEX_HUSH`.

DOUBLE PAGE PRINTING

If the printer has a duplex unit installed, duplex printing can be demanded with the `-d` option.

Otherwise, the command line option `-D` causes the printer to print in doublepage mode, that is, roughly speaking, printing first the even pages and then the odd pages of a document. If `-D` is used to print both even and odd pages (`-D` is used without the optional 1 or 2) the following will happen after half of the pages is printed: LJ: the printer stops, shows message "FEED" and switches on manual feed led. The printer continues when either the printed pages are fed into the

manual page feeder, or the operator pushes the continue button (after placing first the printed pages into the paper tray).

If **-D1** was specified only odd pages will be printed, **-D2** can be used for even pages. A trailing **-** (as in **-D-**, **-D1-** or **-D2-**) suppresses printing of empty pages which are generated for padding otherwise.

The driver allows the **-D** option for both print-directions (front-to-back or back-to-front printing). It tries to be clever in certain cases: when a document has an odd number of pages it inserts in the right place an empty page when a document starts with page 0 the driver inserts an empty page after the 0-page when a piece of a document is printed that starts with an even page-number it prints this page at the backside of the first page to ensure that the odd sides are always on the frontside. The 0-page is treated like an odd page.

The doubleside option works for all LJs, not only for the new D model with does doubleside-printing (actually, I don't know whether it makes much sense on the new LJ II D at all).

Caveat on the doubleside-option: When it is used frequently or on very large files, it might become necessary to clean the printer much more frequently.

The command line option **-pX** can be used to abort printing after the output of *X* pages (can lead to strange results together with **-D**). I personally dislike this option. The secure way of printing a part of a document is using **-f** (from) and **-t** (to).

ENVIRONMENT

dvilj uses the same environment variables and algorithms for finding font files as TeX and its friends do. See the documentation for the *kpathsea* (3) library for details. (Repeating it here is too cumbersome.)

DVILJFONTS

If set, overrides all other font paths.

DVILJMAKEPK

If set, overrides *mktexpk* (1) as the name of the command to execute to create a PK file if one isn't found.

DVILJSIZES

May be set to indicate which sizes of fonts are available. It should consist of a list of numbers separated by colons. If the list begins with a colon, the system default sizes are used, as well. Sizes are expressed in dots per inch; decimals may be used for *pxl* files: for example, a 300 dots per inch file magnified by half a step comes out to 1643 dots per five inches, which should be encoded as 328.6. **dvilj** tries the actual size of the font before trying any of the given sizes.

DVILJINPUTS

Primary search path for include files.

TEXINPUTS

Secondary search path for include files.

TEX_HUSH

Colon separated list of identifiers that name situations where no warning shall be output. The following identifiers are used:

```
checksum  suppress mismatched font checksum warnings
readable  suppress warnings about unreadable files
special   suppress warnings about unknown specials
all       suppress all warning classes above
none      suppress no warnings
```

KPATHSEA_DEBUG

Trace *kpathsea* (3) lookups; set to `-1` for complete tracing.

GS_PATH

On Windows, this may be the path to Ghostscript; there the default is *gswin32c.exe*.

On Unix, this environment variable is not used. Ghostscript is called as *gs*(1) and must be found over `$PATH`.

SEE ALSO

dvihp (1), *dvicopy* (1), *dvips* (1), *xdvi* (1), *mktexpk* (1), *gs* (1), *kpathsea* (3)

Email bug reports to `tex-k@tug.org`.

Source is at `<http://mirror.ctan.org/dviware/dviljk/>`; but for compilation the `texk` build environment is needed, from `<svn://tug.org/texlive/*/Build/source>`.

As of July 2007, PCL reference documentation is found at HP's Web site at `<http://h20000.www2.hp.com/bizsupport/TechSupport/Document.jsp?objectID=bpl04568>`. At the end of that page are links to reference manuals for PCL and PjL.

In case that page is changed, here are the URLs of these documents. All have the form `<http://h20000.www2.hp.com/bc/docs/support/SupportManual/bpl<ID>/bpl<ID>.pdf>`, where `<ID>` is the following document ID:

13205

PCL 5 Technical Quick Reference Guide. This is the 1st thing to look up if you have questions about PCL escape sequences.

13210 and 13211

PCL 5 Technical Reference Manual (part I and II). This is the full-detailed explanation that you need to look up if you don't understand how the printer works. Part I is the actual manual, part II explains HP-GL/2 and has overall tips.

13208 and 13207

PjL Technical Reference Manual (and addendum)

13212

PCL 5 Color Manual. This explains color specials for the newer HP printers. (Not of much use today; for practical purposes we would need to add color specials to **dvilj** first.)

13206 and 13209

Comparison Guide (and addendum) that documents which PCL escape sequences are supported on which HP printers.

AUTHOR

`dvi2xx` by Gustaf Neumann, Wirtschaftsuniversitaet Wien.

`dviljk` fork by Karl Berry.

Joachim Schrod `<jschrod@acm.org>` supplied security fixes and updated this man page.

LICENSE

dvi2xx is public domain software. dvi2x changes are covered by the GNU General Public License.

POD ERRORS

Hey! **The above document had some coding errors, which are explained below:**

Around line 595:

You forgot a '=back' before '=head1'