PS_VIEW COMMANDS LIST (1)

(press PgDn or Esc)

PARAMETERS	COMMAND	ALIASES	DESCRIPTION
(FILE_NAME)	o	a	open new picture
(FILE_NAME)	op	ap	open new paged document
	c	F10	redraw current picture
	i	F11	initial parameter settings
	w	F12	view whole picture
{(FILE_NAME)}	wr	F2	write the restart information
{(FILE_NAME)}	rr	F3	read the restart information
{PAGE}	pn	np F4	go to the specified page
	pf	fp Home	go to the first page
	pl	lp End	go to the last page
{INCR}	n	PgDn	go to the next page
{INCR}	p	PgUp	go to the previous page
{MAG}	m		set magnification factor
	g		draw grid
{HOR} {VER}	v		view magnified and shifted picture
{HOR} {VER}	vu	Alt .	magnify picture (≡ 'v')
{HOR} {VER}	vd	Alt ,	diminish picture (≡ 'v' with scaling $= \frac{1}{\mathrm{MAG}}$)
{HOR} {VER}	go	Tab	shift screen (≡ 'v' with scaling = 1)

PS_VIEW COMMANDS LIST (2) (press PgUp , PgDn or Esc)

PARAMETERS	COMMAND	ALIASES	DESCRIPTION
{SHIFT}	s		set shift
{SHIFT}	l	←	shift picture left
{SHIFT}	r	→	shift picture right
{SHIFT}	u	↑	shift picture up
{SHIFT}	d	↓	shift picture down
{STEP}	ro	Shift Tab	rotate by STEP $\times$ 90
	hf		flip picture horizontaly
	vf		flip picture verticaly
{INCR}	un	Del	undo previous picture
{INCR}	re	Ins	redo undone picture
	fr		show frame (approximate printing area)
{(FILE_NAME)}	pr	Ctrl Print Scr	print screen or send it to a file
DEVICE_NAME	prs		select printer (used by 'pr')
	r1024		set resolution (TVGA and TSENG)
	r800		set resolution (TVGA and TSENG)
	r640		set resolution (TVGA and TSENG)
	rsc	F9	reset screen

PS_VIEW COMMANDS LIST (3) (press PgUp or Esc)

PARAMETERS	COMMAND	ALIASES	DESCRIPTION
	e		attempt to recover from error
	q	Ctrl Q Alt Q Alt F4	quit saving the restart
	x	Ctrl X Alt X Esc	exit without saving the restart
	hlp	Alt H F1	help

Remark 1: In curly braces appear optional parameters.
Remark 2: Sequences in frames (keys) do not need pressing Enter ,
but they require ANSI.SYS to be installed.
Remark 3: Some commands are inactive or their meanings are changed
as long as the help is on.