

The pdfcolparcolumns package

Heiko Oberdiek
<oberdiek@uni-freiburg.de>

2008/08/11 v1.2

Abstract

Since version 1.40 pdfTeX supports several color stacks. This package uses them to fix color problems in package `parcolumns`.

Contents

| | | |
|----------|---|----------|
| 1 | Usage | 1 |
| 1.1 | Future | 2 |
| 2 | Implementation | 2 |
| 2.1 | Identification | 2 |
| 2.2 | Load packages | 2 |
| 2.2.1 | Package <code>parcolumns</code> | 2 |
| 2.2.2 | Package <code>pdfcol</code> | 2 |
| 2.2.3 | Package <code>infwarerr</code> | 2 |
| 2.3 | Color stack macros | 2 |
| 2.4 | Patches | 3 |
| 2.4.1 | Init stacks | 3 |
| 2.4.2 | Switch stack | 3 |
| 2.4.3 | Set current stack color | 3 |
| 3 | Test | 5 |
| 4 | Installation | 5 |
| 4.1 | Download | 5 |
| 4.2 | Bundle installation | 6 |
| 4.3 | Package installation | 6 |
| 4.4 | Refresh file name databases | 6 |
| 4.5 | Some details for the interested | 6 |
| 5 | References | 7 |
| 6 | History | 7 |
| | [2007/07/26 v1.0] | 7 |
| | [2007/09/09 v1.1] | 7 |
| | [2008/08/11 v1.2] | 7 |
| 7 | Index | 7 |

1 Usage

`\usepackage{pdfcolparcolumns}`

The package `pdfcolparcolumns` loads package `parcolumns` [1]. If color stacks are available then the macros of `parcolumns` are patched to add support for color stacks.

1.1 Future

Currently package `parcolumns` does not seem to be maintained. Nevertheless if there will be a new version that adds support for color stacks, then this package may become obsolete.

2 Implementation

2.1 Identification

```
1 (*package)
2 \NeedsTeXFormat{LaTeX2e}
3 \ProvidesPackage{pdfcolparcolumns}%
4 [2008/08/11 v1.2 Color stacks support for parcolumns (HO)]%
```

2.2 Load packages

2.2.1 Package `parcolumns`

Currently package `parcolumns` does not define options. Thus it is just a precaution that the options of package `pdfcolparcolumns` are passed to package `parcolumns`.

```
5 \DeclareOption*{%
6   \PassOptionsToPackage{\CurrentOption}{parcolumns}%
7 }
8 \ProcessOptions\relax
9 \RequirePackage{parcolumns}[2004/11/25]
```

2.2.2 Package `pdfcol`

```
10 \RequirePackage{pdfcol}[2007/09/09]
11 \ifpdfcolAvailable
12 \else
13   \PackageInfo{pdfcolparcolumns}{%
14     Loading aborted, because color stacks are not available%
15   }%
16   \expandafter\endinput
17 \fi
```

2.2.3 Package `infwarerr`

```
18 \RequirePackage{infwarerr}[2007/09/09]
```

2.3 Color stack macros

`\pcpc@MaxStack` Macro `\pcpc@MaxStack` holds the highest number of allocated stacks.

```
19 \global\chardef\pcpc@MaxStack=\z@
```

`\pcpc@InitStacks` Macro `\pcpc@InitStacks` takes the number of columns as argument and ensures that there are enough color stacks for all columns.

```
20 \def\pcpc@InitStacks#1{%
21   \ifnum#1>\pcpc@MaxStack
22     \begingroup
23       \count@\pcpc@MaxStack
24       \loop
25         \advance\count@\@ne
26         \pdfcolInitStack{pcpc@\the\count@}%
27       \ifnum#1>\count@
28         \repeat
29       \global\chardef\pcpc@MaxStack=\count@
30     \endgroup
31   \fi
32 }
```

`\pcpc@SwitchStack`

```
33 \def\pcpc@SwitchStack#1{%
34   \pdfcolSwitchStack{pcpc@\number#1}%
35 }
```

`\pcpc@SetCurrent`

```
36 \def\pcpc@SetCurrent#1{%
37   \pdfcolSetCurrent{pcpc@\number#1}%
38 }
```

2.4 Patches

Now the color stack macros are patched into the macros of package `parcolumns`.

2.4.1 Init stacks

`\pcpc@InitStacks` should go into the definition of environment `parcolumns`. `\pc@allocccolumns` is executed there and nowhere else, thus we hook into it.

```
39 \g@addto@macro\pc@allocccolumns{%
40   \pcpc@InitStacks\pc@columncount
41 }
```

2.4.2 Switch stack

`\pcpc@SwitchStack` should be called by macro `\colchunk@`. However it is easier to patch `\pc@setcolumnwidth` that is executed in `\colchunk@` only.

```
42 \g@addto@macro\pc@setcolumnwidth{%
43   \pcpc@SwitchStack\pc@columnctr
44 }
```

2.4.3 Set current stack color

`\pcpc@SetCurrent` is set at the begin of each line. It must be inserted into `\pc@placeboxes`. Unhappily there is no easy way. Therefore we check and redefine `\pc@placeboxes`.

```
45 \begin{group}
46   \def\x{%
47     \global\let\@tempa\relax
48     \count@\z@
49     \hb@xt@\linewidth{%
50       \vfuzz30ex %
51       \vbadness\@M
52       \splittopskip\z@skip
53       \loop
54       \ifnum\count@<\pc@columncount
55         \advance\count@\@ne
56         \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
57           \hskip\csname pc@column@width@\number\count@\endcsname
58         \else
59           \expandafter\setbox\expandafter\@tempboxa\expandafter
60             \vsplit\csname pc@column@\number\count@\endcsname
61             to \dp\strutbox
62           \vbox{%
63             \unvbox\@tempboxa
64           }%
65         \fi
66         \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
67         \else
68           \global\let\@tempa\pc@placeboxes
69         \fi
70       \ifnum\count@<\pc@columncount
```

```

71         \strut
72         \hfill
73         \ifpc@rulebetween
74         \vrule
75         \hfill
76         \fi
77     \fi
78     \repeat
79 }%
80 \@tempa
81 }%
82 \ifx\x\pc@placeboxes
83 \else
84   \@PackageWarningNoLine{pdfcolparcolumns}{%
85     Command \string\pc@placeboxes\space has changed.\MessageBreak
86     Supported versions of package 'parcolumns':\MessageBreak
87     \space\space 2004/08/05.\MessageBreak
88     The redefinition of \string\pc@placeboxes\space may not%
89     \MessageBreak
90     behave correctly depending on the changes%
91   }%
92 \fi
93 \endgroup

```

\pc@placeboxes

```

94 \renewcommand*{\pc@placeboxes}{%
95   \global\let\@tempa\relax
96   \count@\z@
97   \hb@xt@\linewidth{%
98     \vfuzz30ex %
99     \vbadness\@M
100    \splittopskip\z@skip
101    \loop
102      \ifnum\count@<\pc@columncount
103        \advance\count@\@ne
104        \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
105          \hskip\csname pc@column@width@\number\count@\endcsname
106        \else
107          \expandafter\setbox\expandafter\@tempboxa\expandafter
108            \vsplit\csname pc@column@\number\count@\endcsname
109            to \dp\strutbox
110          \vbox{%
111            \pcpc@SetCurrent\count@
112            \unvbox\@tempboxa
113          }%
114        \fi
115        \expandafter\ifvoid\csname pc@column@\number\count@\endcsname
116        \else
117          \global\let\@tempa\pc@placeboxes
118        \fi
119        \ifnum\count@<\pc@columncount
120          \strut
121          \hfill
122          \ifpc@rulebetween
123          \vrule
124          \hfill
125        \fi
126      \fi
127    \repeat
128  }%
129  \@tempa
130 }

```

```
131 </package>
```

3 Test

The test file is a modified version of the file that Donald Goodman has posted in [comp.text.tex](#): “Re: xcolor glitches”¹

```
132 <test1>
133 \NeedsTeXFormat{LaTeX2e}
134 \AtEndDocument{%
135   \typeout{%
136     \typeout{*****}%
137     \typeout{*** \space Check the PDF file manually! \space ***}%
138     \typeout{*****}%
139   \typeout}%
140 }
141 \documentclass{article}
142 \usepackage{xcolor}
143 \usepackage{pdfcolparcolumns}
144
145 \newcommand{\instruct}[1]{%
146   \noindent
147   \footnotesize
148   \textcolor{red}{#1}%
149 }
150
151 \begin{document}
152   \begin{parcolumns}[colwidths={1=2.3in,2=2.3in},sloppy]{2}%
153     \colchunk[1]{%
154       \instruct{Et non dicitur versus} %
155       Fidelium anim\ae %
156       \instruct{%
157         sed immediate subiungitur antiphona finalis %
158         beat\ae\ Mari\ae\ Virginis%
159       } %
160       100.%
161     }%
162     \colchunk[2]{%
163       \instruct{%
164         And the verse %
165         \textcolor{black}{May the souls of the faithful} %
166         is not said, but the final antiphon of the %
167         Blessed Virgin Mary, %
168         \textcolor{black}{100,} %
169         is immediately joined.%
170       }%
171     }%
172   \end{parcolumns}%
173 \end{document}
174 </test1>
```

4 Installation

4.1 Download

Package. This package is available on CTAN²:

[CTAN:macros/latex/contrib/oberdiek/pdfcolparcolumns.dtx](#) The source file.

[CTAN:macros/latex/contrib/oberdiek/pdfcolparcolumns.pdf](#) Documentation.

¹Url: <http://groups.google.com/group/comp.text.tex/msg/8eda74ed292012bb>

²<ftp://ftp.ctan.org/tex-archive/>

Bundle. All the packages of the bundle ‘oberdiek’ are also available in a TDS compliant ZIP archive. There the packages are already unpacked and the documentation files are generated. The files and directories obey the TDS standard.

[CTAN:install/macros/latex/contrib/oberdiek.tds.zip](#)

TDS refers to the standard “A Directory Structure for T_EX Files” ([CTAN:tds/tds.pdf](#)). Directories with `texmf` in their name are usually organized this way.

4.2 Bundle installation

Unpacking. Unpack the `oberdiek.tds.zip` in the TDS tree (also known as `texmf` tree) of your choice. Example (linux):

```
unzip oberdiek.tds.zip -d ~/texmf
```

Script installation. Check the directory `TDS:scripts/oberdiek/` for scripts that need further installation steps. Package `attachfile2` comes with the Perl script `pdfatfi.pl` that should be installed in such a way that it can be called as `pdfatfi`. Example (linux):

```
chmod +x scripts/oberdiek/pdfatfi.pl
cp scripts/oberdiek/pdfatfi.pl /usr/local/bin/
```

4.3 Package installation

Unpacking. The `.dtx` file is a self-extracting `docstrip` archive. The files are extracted by running the `.dtx` through plain-T_EX:

```
tex pdfcolparcolumns.dtx
```

TDS. Now the different files must be moved into the different directories in your installation TDS tree (also known as `texmf` tree):

| | |
|--|---|
| <code>pdfcolparcolumns.sty</code> | → <code>tex/latex/oberdiek/pdfcolparcolumns.sty</code> |
| <code>pdfcolparcolumns.pdf</code> | → <code>doc/latex/oberdiek/pdfcolparcolumns.pdf</code> |
| <code>test/pdfcolparcolumns-test1.tex</code> | → <code>doc/latex/oberdiek/test/pdfcolparcolumns-test1.tex</code> |
| <code>pdfcolparcolumns.dtx</code> | → <code>source/latex/oberdiek/pdfcolparcolumns.dtx</code> |

If you have a `docstrip.cfg` that configures and enables `docstrip`’s TDS installing feature, then some files can already be in the right place, see the documentation of `docstrip`.

4.4 Refresh file name databases

If your T_EX distribution (teT_EX, miK_TE_X, ...) relies on file name databases, you must refresh these. For example, teT_EX users run `texhash` or `mktextlsr`.

4.5 Some details for the interested

Attached source. The PDF documentation on CTAN also includes the `.dtx` source file. It can be extracted by AcrobatReader 6 or higher. Another option is `pdftk`, e.g. unpack the file into the current directory:

```
pdftk pdfcolparcolumns.pdf unpack_files output .
```

Unpacking with L^AT_EX. The `.dtx` chooses its action depending on the format:
plain-T_EX: Run `docstrip` and extract the files.

L^AT_EX: Generate the documentation.

If you insist on using L^AT_EX for `docstrip` (really, `docstrip` does not need L^AT_EX), then inform the autodetect routine about your intention:

```
latex \let\install=y\input{pdfcolparcolumns.dtx}
```

Do not forget to quote the argument according to the demands of your shell.

Generating the documentation. You can use both the `.dtx` or the `.drv` to generate the documentation. The process can be configured by the configuration file `ltxdoc.cfg`. For instance, put this line into this file, if you want to have A4 as paper format:

```
\PassOptionsToClass{a4paper}{article}
```

An example follows how to generate the documentation with pdfL^AT_EX:

```
pdflatex pdfcolparcolumns.dtx
makeindex -s gind.ist pdfcolparcolumns.idx
pdflatex pdfcolparcolumns.dtx
makeindex -s gind.ist pdfcolparcolumns.idx
pdflatex pdfcolparcolumns.dtx
```

5 References

- [1] Jonathan Sauer: *The parcolumns package*; 2004/11/25;
CTAN:macros/latex/contrib/sauerj/parcolumns.pdf.
- [2] Heiko Oberdiek: *The pdfcol package*; 2007/09/09;
CTAN:macros/latex/contrib/oberdiek/pdfcol.pdf.

6 History

[2007/07/26 v1.0]

- First version, published in the newsgroup `comp.text.tex` with the name `parcolumns-colorstacks`: “[Re: xcolor glitches](#)”³

[2007/09/09 v1.1]

- CTAN version, package name renamed to `pdfcolparcolumns`.
- Uses package `pdfcol`.
- Documentation added.
- Test file added.

[2008/08/11 v1.2]

- Code is not changed.
- URLs updated.

7 Index

Numbers written in *italic* refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

Symbols

| | | | |
|---|--------------------------|-----------------------------------|-------------|
| <code>\@M</code> | 51, 99 | <code>_</code> | 155, 158 |
| <code>\@PackageWarningNoLine</code> | 84 | | |
| <code>\@ne</code> | 25, 55, 103 | A | |
| <code>\@tempa</code> | 47, 68, 80, 95, 117, 129 | <code>\advance</code> | 25, 55, 103 |
| <code>\@tempboxa</code> | 59, 63, 107, 112 | <code>\ae</code> | 155, 158 |
| | | <code>\AtEndDocument</code> | 134 |

³Url: <http://groups.google.com/group/comp.text.tex/msg/56bd897b11bca414>

| | | | |
|--------------------|--|-----------------------|-------------------------|
| B | | P | |
| \begin | 151, 152 | \PackageInfo | 13 |
| C | | \PassoptionsToPackage | 6 |
| \chardef | 19, 29 | \pc@alloccolumns | 39 |
| \colchunk | 153, 162 | \pc@columncount | 40, 54, 70, 102, 119 |
| \count@ | 23, 25, 26, 27, 29, 48, 54, 55, 56, 57, 60, 66, 70, 96, 102, 103, 104, 105, 108, 111, 115, 119 | \pc@columnctr | 43 |
| \csname | 56, 57, 60, 66, 104, 105, 108, 115 | \pc@placeboxes | 68, 82, 85, 88, 94 |
| \CurrentOption | 6 | \pc@setcolumnwidth | 42 |
| D | | \pcpc@InitStacks | 20, 40 |
| \DeclareOption | 5 | \pcpc@MaxStack | 19, 21, 23, 29 |
| \documentclass | 141 | \pcpc@SetCurrent | 36, 111 |
| \dp | 61, 109 | \pcpc@SwitchStack | 33, 43 |
| E | | \pdfcolInitStack | 26 |
| \end | 172, 173 | \pdfcolSetCurrent | 37 |
| \endcsname | 56, 57, 60, 66, 104, 105, 108, 115 | \pdfcolSwitchStack | 34 |
| \endinginput | 16 | \ProcessOptions | 8 |
| F | | \ProvidesPackage | 3 |
| \footnotesize | 147 | R | |
| G | | \renewcommand | 94 |
| \g@addto@macro | 39, 42 | \repeat | 28, 78, 127 |
| H | | \RequirePackage | 9, 10, 18 |
| \hb@xt@ | 49, 97 | S | |
| \hfill | 72, 75, 121, 124 | \setbox | 59, 107 |
| \hskip | 57, 105 | \space | 85, 87, 88, 137 |
| I | | \splittopskip | 52, 100 |
| \ifnum | 21, 27, 54, 70, 102, 119 | \strut | 71, 120 |
| \ifpc@rulebetween | 73, 122 | \strutbox | 61, 109 |
| \ifpdfcolAvailable | 11 | T | |
| \ifvoid | 56, 66, 104, 115 | \textcolor | 148, 165, 168 |
| \ifx | 82 | \the | 26 |
| \instruct | 145, 154, 156, 163 | \typeout | 135, 136, 137, 138, 139 |
| L | | U | |
| \linewidth | 49, 97 | \unvbox | 63, 112 |
| \loop | 24, 53, 101 | \usepackage | 142, 143 |
| M | | V | |
| \MessageBreak | 85, 86, 87, 89 | \vbadness | 51, 99 |
| N | | \vbox | 62, 110 |
| \NeedsTeXFormat | 2, 133 | \vfuzz | 50, 98 |
| \newcommand | 145 | \vrule | 74, 123 |
| \noindent | 146 | \vsplit | 60, 108 |
| \number | 34, 37, 56, 57, 60, 66, 104, 105, 108, 115 | X | |
| X | | \x | 46, 82 |
| Z | | Z | |
| | | \z@ | 19, 48, 96 |
| | | \z@skip | 52, 100 |